

Procedure

Computer Organization and Assembly Languages
Yung-Yu Chuang
2006/11/13


with slides by Kip Irvine

Chapter overview

- Linking to an External Library
- The Book's Link Library
- Stack Operations
- Defining and Using Procedures
- Program Design Using Procedures


Announcements

- Midterm examination will be held from 10-12 in Room 103 on 11/20. It is an openbook exam.
- Scope: what I have taught till chapter 5



The book's link library


Calling a library procedure



- Call a library procedure using the CALL instruction.
Some procedures require input arguments. The INCLUDE directive copies in the procedure prototypes (declarations).
- The following example displays "1234" on the console:

```
INCLUDE Irvine32.inc
.code
    mov eax,1234h      ; input argument
    call WriteHex       ; show hex number
    call Crlf           ; end of line
```

Library procedures - overview (1 of 3)



Clscr - Clears the console and locates the cursor at the upper left corner.

Crlf - Writes an end of line sequence to standard output.

Delay - Pauses the program execution for a specified *n* millisecond interval.


DumpMem - Writes a block of memory to standard output in hexadecimal.

DumpRegs - Displays the EAX, EBX, ECX, EDX, ESI, EDI, EBP, ESP, EFLAGS, and EIP registers in hexadecimal. Also displays the Carry, Sign, Zero, and Overflow flags.


GetCommandtail - Copies the program's command-line arguments (called the *command tail*) into an array of bytes.

GetMseconds - Returns the number of milliseconds that have elapsed since midnight.


Linking to a library



- Your programs link to Irvine32.lib using the linker command inside a batch file named make32.bat.
- Notice the two LIB files: Irvine32.lib, and kernel32.lib
 - the latter is part of the Microsoft *Win32 Software Development Kit*



Library procedures - overview (2 of 3)



Gotoxy - Locates cursor at row and column on the console.

Random32 - Generates a 32-bit pseudorandom integer in the range 0 to FFFFFFFFh.

Randomize - Seeds the random number generator.

RandomRange - Generates a pseudorandom integer within a specified range.

ReadChar - Reads a single character from standard input.

ReadHex - Reads a 32-bit hexadecimal integer from standard input, terminated by the Enter key.

ReadInt - Reads a 32-bit signed decimal integer from standard input, terminated by the Enter key.

ReadString - Reads a string from standard input, terminated by the Enter key.

Library procedures - overview (3 of 3)

SetTextColor - Sets the foreground and background colors of all subsequent text output to the console.

WaitMsg - Displays message, waits for Enter key to be pressed.

WriteBin - Writes an unsigned 32-bit integer to standard output in ASCII binary format.

WriteChar - Writes a single character to standard output.

WriteDec - Writes an unsigned 32-bit integer to standard output in decimal format.

WriteHex - Writes an unsigned 32-bit integer to standard output in hexadecimal format.

WriteInt - Writes a signed 32-bit integer to standard output in decimal format.

WriteString - Writes a null-terminated string to standard output.

Example 2

Display a null-terminated string and move the cursor to the beginning of the next screen line.

```
.data  
str1 BYTE "Assembly language is easy!",0  
  
.code  
    mov  edx,OFFSET str1  
    call WriteString  
    call Crlf
```



Example 1

Clear the screen, delay the program for 500 milliseconds, and dump the registers and flags.

```
.code  
    call Clrscr  
    mov  eax,500  
    call Delay  
    call DumpRegs
```



Sample output:

```
EAX=00000613 EBX=00000000 ECX=000000FF EDX=00000000  
ESI=00000000 EDI=00000100 EBP=0000091E ESP=000000F6  
EIP=00401026 EFL=00000286 CF=0 SF=1 ZF=0 OF=0
```

Example 3

Display the same unsigned integer in binary, decimal, and hexadecimal. Each number is displayed on a separate line.


```
IntVal = 35 ; constant  
.code  
    mov  eax,IntVal  
    call WriteBin ; display binary  
    call Crlf  
    call WriteDec ; display decimal  
    call Crlf  
    call WriteHex ; display hexadecimal  
    call Crlf
```



Sample output:

```
0000 0000 0000 0000 0000 0000 0010 0011  
35  
23
```


Example 4



Input a string from the user. EDX points to the string and ECX specifies the maximum number of characters the user is permitted to enter.

```
.data  
fileName BYTE 80 DUP(0)  
  
.code  
    mov edx,OFFSET fileName  
    mov ecx,SIZEOF fileName - 1  
    call ReadString
```

Example 6




Display a null-terminated string with yellow characters on a blue background.

```
.data  
str1 BYTE "Color output is easy!",0  
  
.code  
    mov eax,yellow + (blue * 16)  
    call SetTextColor  
    mov edx,OFFSET str1  
    call WriteString  
    call Crlf
```

The background color must be multiplied by 16 before you add it to the foreground color.

Example 5



Generate and display ten pseudorandom signed integers in the range 0 - 99. Each integer is passed to WriteInt in EAX and displayed on a separate line.

```
.code  
    mov ecx,10           ; loop counter  
  
L1:  
    mov eax,100          ; ceiling value  
    call RandomRange     ; generate random int  
    call WriteInt         ; display signed int  
    call Crlf             ; goto next display line  
    loop L1               ; repeat loop
```

Stack operations


Stacks

- LIFO (Last-In, First-Out) data structure.
- push/pop operations
- You probably have had experiences on implementing it in high-level languages.
- Here, we concentrate on *runtime stack*, directly supported by hardware in the CPU. It is essential for calling and returning from procedures.



Runtime stack

- Managed by the CPU, using two registers
 - SS (stack segment)
 - ESP (stack pointer) * : point to the top of the stack usually modified by **CALL**, **RET**, **PUSH** and **POP**



* SP in Real-address mode


PUSH and POP instructions

- **PUSH** syntax:
 - **PUSH r/m16**
 - **PUSH r/m32**
 - **PUSH imm32**
- **POP** syntax:
 - **POP r/m16**
 - **POP r/m32**





PUSH operation (1 of 2)

- A **p**ush operation decrements the stack pointer by 2 or 4 (depending on operands) and copies a value into the location pointed to by the stack pointer.





PUSH operation (2 of 2)

- The same stack after pushing two more integers:



POP operation

- Copies value at stack[ESP] into a register or variable.
- Adds n to ESP, where n is either 2 or 4, depending on the attribute of the operand receiving the data



When to use stacks

- Temporary save area for registers
- To save return address for CALL
- To pass arguments
- Local variables
- Applications which have LIFO nature, such as reversing a string

Example of using stacks

Save and restore registers when they contain important values. Note that the **PUSH** and **POP** instructions are in the opposite order:

```
push esi           ; push registers
push ecx
push ebx

mov esi,OFFSET dwordVal ; starting OFFSET
mov ecx,LENGTHOF dwordVal; number of units
mov ebx,TYPE dwordVal ;size of a doubleword
call DumpMem         ; display memory

pop ebx            ; opposite order
pop ecx
pop esi
```

Example: Nested Loop



When creating a nested loop, push the outer loop counter before entering the inner loop:

```
    mov ecx,100      ; set outer loop count
L1:                           ; begin the outer loop
    push ecx        ; save outer loop count

    mov ecx,20       ; set inner loop count
L2:                           ; begin the inner loop
;
;
    loop L2         ; repeat the inner loop

    pop ecx        ; restore outer loop count
loop L1          ; repeat the outer loop
```

Example: reversing a string



```
; Pop the name from the stack, in reverse,
; and store in the aName array.
    mov ecx,nameSize
    mov esi,0

L2:
    pop eax          ; get character
    mov aName[esi],al ; store in string
    inc esi
Loop L2

    exit
main ENDP
END main
```

Example: reversing a string



```
.data
aName BYTE "Abraham Lincoln",0
nameSize = ($ - aName) - 1

.code
main PROC
; Push the name on the stack.
    mov ecx,nameSize
    mov esi,0
L1:
    movzx eax,aName[esi]    ; get character
    push eax                ; push on stack
    inc esi
Loop L1
```

Related instructions



- **PUSHFD** and **POPFD**
 - push and pop the EFLAGS register
 - **LAHF**, **SAHF** are other ways to save flags
- **PUSHAD** pushes the 32-bit general-purpose registers on the stack
 - order: EAX, ECX, EDX, EBX, ESP, EBP, ESI, EDI
- **POPAD** pops the same registers off the stack in reverse order
 - **PUSHA** and **POPA** do the same for 16-bit registers

Example

```
MySub PROC
    pushad
    ...
    ; modify some register
    ...
    popad
    ret
Do not use this if your procedure uses
registers for return values
MySub ENDP
```



Creating Procedures

- Large problems can be divided into smaller tasks to make them more manageable
- A procedure is the ASM equivalent of a Java or C++ function
- Following is an assembly language procedure named sample:

```
sample PROC
    .
    .
    ret
sample ENDP
```



A named block of statements that ends with a return.

Defining and using procedures

Documenting procedures



- Suggested documentation for each procedure:
- A description of all tasks accomplished by the procedure.
 - Receives: A list of input parameters; state their usage and requirements.
 - Returns: A description of values returned by the procedure.
 - Requires: Optional list of requirements called preconditions that must be satisfied before the procedure is called.

For example, a procedure of drawing lines could assume that display adapter is already in graphics mode.

Example: SumOf procedure

```
;-----  
SumOf PROC  
;  
; Calculates and returns the sum of three 32-bit  
; integers.  
; Receives: EAX, EBX, ECX, the three integers.  
; May be signed or unsigned.  
; Returns: EAX = sum, and the status flags  
; (Carry, Overflow, etc.) are changed.  
; Requires: nothing  
;  
    add eax,ebx  
    add eax,ecx  
    ret  
SumOf ENDP  
;-----
```



CALL and RET instructions

- The **CALL** instruction calls a procedure
 - pushes offset of next instruction on the stack
 - copies the address of the called procedure into EIP
- The **RET** instruction returns from a procedure
 - pops top of stack into EIP
- We used **j1** and **jr** in our toy computer for **CALL** and **RET**?

CALL-RET example (1 of 2)

0000025 is the offset
of the instruction
immediately following
the CALL instruction


```
main PROC  
    00000020 call MySub  
    00000025 mov eax,ebx  
    .  
    .  
main ENDP  
  
MySub PROC  
    00000040 mov eax,edx  
    .  
    .  
    ret  
MySub ENDP
```

00000040 is the offset
of the first instruction
inside MySub




CALL-RET example (2 of 2)



The CALL instruction
pushes 00000025 onto
the stack, and loads
00000040 into EIP



The RET instruction
pops 00000025 from
the stack into EIP



Nested procedure calls




Local and global labels

A local label is visible only to statements inside the same procedure. A global label is visible everywhere.

```
main PROC
    jmp L2 ; error!
L1:: ; global label
    exit
main ENDP

sub2 PROC
L2: ; local label
    jmp L1 ; ok
    ret
sub2 ENDP
```



Procedure parameters (1 of 3)

- A good procedure might be usable in many different programs
- Parameters help to make procedures flexible because parameter values can change at runtime
- General registers can be used to pass parameters




Procedure parameters (2 of 3)

The ArraySum procedure calculates the sum of an array. It makes two references to specific variable names:

```
ArraySum PROC
    mov esi,0 ; array index
    mov eax,0 ; set the sum to zero

L1:
    add eax,myArray[esi] ; add each integer to sum
    add esi,4 ; point to next integer
    loop L1 ; repeat for array size

    mov theSum,eax ; store the sum
    ret
ArraySum ENDP
```



Procedure parameters (3 of 3)



This version returns the sum of any doubleword array whose address is in ESI. The sum is returned in EAX:

```
ArraySum PROC
; Recevies: ESI points to an array of doublewords,
;           ECX = number of array elements.
; Returns:   EAX = sum
;-----
    push esi
    push ecx
    mov eax,0          ; set the sum to zero
L1: add eax,[esi]      ; add each integer to sum
    add esi,4          ; point to next integer
    loop L1            ; repeat for array size
    Pop ecx
    Pop esi
    ret

ArraySum ENDP
```

USES operator



- Lists the registers that will be saved (to avoid side effects) (return register shouldn't be saved)

```
ArraySum PROC USES esi ecx
    mov eax,0 ; set the sum to zero
    ...
    ...
```

MASM generates the following code:

```
ArraySum PROC
    push esi
    push ecx
    .
    .
    pop ecx
    pop esi
    ret
ArraySum ENDP
```

Calling `ArraySum`



```
.data
array DWORD 10000h, 20000h, 30000h, 40000h
theSum DWORD ?

.code
main PROC
    mov     esi, OFFSET array
    mov     ecx, LENGTHOF array
    call    ArraySum
    mov     theSum, eax
    ret
```

-

Program design using procedures



- Top-Down Design (functional decomposition) involves the following:
 - design your program before starting to code
 - break large tasks into smaller ones
 - use a hierarchical structure based on procedure calls
 - test individual procedures separately

Integer summation program (1 of 4)




Spec.: Write a program that prompts the user for multiple 32-bit integers, stores them in an array, calculates the sum of the array, and displays the sum on the screen.

Main steps:

- Prompt user for multiple integers
- Calculate the sum of the array
- Display the sum

Structure chart (3 of 4)



Procedure design (2 of 4)



Main

```
Clscr ; clear screen
PromptForIntegers
  WriteString ; display string
  ReadInt ; input integer
  ArraySum ; sum the integers
  DisplaySum
    WriteString ; display string
    Writeln ; display integer
```

PromptForIntegers



```
;-----
; PromptForIntegers PROC
;
; Prompts the user for an array of integers, and
; fills the array with the user's input.
; Receives: ESI points to the array,
;           ECX = array size
; Returns: nothing
;-----
pushad ; save all registers

mov edx,OFFSET prompt1 ; address of the prompt
cmp ecx,0 ; array size <= 0?
jle L2 ; yes: quit
```


PromptForIntegers

```
L1:  
    call WriteString      ; display string  
    call ReadInt         ; read integer into EAX  
    call Crlf            ; go to next output line  
    mov  [esi],eax        ; store in array  
    add  esi,4            ; next integer  
    loop L1  
  
L2:  
    popad                ; restore all registers  
    ret  
PromptForIntegers ENDP
```



PromptForIntegers

```
;-----  
DisplaySum PROC  
; Displays the sum on the screen  
; Receives: EAX = the sum  
; Returns: nothing  
;-----  
    push edx  
    mov  edx,OFFSET prompt2 ; display message  
    call WriteString  
    call WriteInt          ; display EAX  
    call Crlf  
    pop  edx  
    ret  
DisplaySum ENDP
```



Code fragment

```
IntegerCount = 3           ; array size  
.data  
prompt1 BYTE  "Enter a signed integer: ",0  
prompt2 BYTE  "The sum of the integers is: ",0  
array    DWORD IntegerCount DUP(?)  
.code  
main PROC  
    call Clrscr  
    mov  esi,OFFSET array  
    mov  ecx,IntegerCount  
    call PromptForIntegers  
    call ArraySum  
    call DisplaySum  
    exit  
main ENDP
```



Sample output (4 of 4)

```
Enter a signed integer: 550  
Enter a signed integer: -23  
Enter a signed integer: -96  
The sum of the integers is: +431
```

